

# Topodroid Device Settings

Marco Corvi

[marco.corvi@gmail.com](mailto:marco.corvi@gmail.com)

2017

# Device settings (1)

- Bluetooth
  - disabled
  - check on startup [default]
  - enabled
- Data transfer mode
  - On demand [default]
  - Continuous
  - Multi-DistoX
- Auto-reconnect (**on**/off) for continuous data mode

# Device settings (2)

- Socket type
  - Default
  - Insecure (Samsung)
- Z6 workaround (**on/off**)
- Connection delay (**0**)
- Auto-pairing (**on/off**)
- Data pause [**250** ms]
- Data ready wait delay [**500** ms]

# Device settings (3)

- Laser pause [**1000** ms]
  - Pause after turning on the laser
- Shot pause [**4000** ms]
  - Pause after taking a measurement

# See also

- Calibration settings